




1→ Format the SD-Card in this way:





2→ Open the file "SD_CARD_V1_9.zip" using WinZip:



3→ Select all zipped files using “CTRL+A”




4→ Press "SHIFT+E" to extract all the files into your SD-Card



5→ Close WinZip

6→ Check that the structure of your SD-Card is now as shown in the following figure:



7→ Insert your SD into USB Tester.

8→ Connect your USB Tester by the mini USB cable to your PC, your USB Tester will switch ON.

9→ Wait until the yellow and red LEDs stop blinking and the green and yellow LEDs are ON.

10→ Your USB tester is now Up-graded to version 1.9.